

# How to change my 4PSA DNS Manager HTTP server SSL certificate

This article describes how to change the digital certificate used by your 4PSA DNS Manager 3 (or later version) HTTP server.

## Requirements

Before you start, make sure that the following requirements are met:

- You have a 4PSA DNS Manager version higher than 3.0.0 (e.g. 4.0.0)
- You have access and basic knowledge for using a SSH client (e.g. Putty)

## Changing the Server's SSL certificate

To change the digital certificate used by your HTTP server, you have to create a signing request, send the request to your CA authority and then install the new certificate on your server:

**STEP 1:** Log in to your 4PSA DNS Manager server using your favorite SSH console (e.g. Putty).

**STEP 2:** Create the signing request for the certificate by executing the command:

```
openssl req -new -key /usr/local/dnsmanager/admin/conf/httpd.pem -out certrequest.csr
```

**STEP 3:** Send the `certrequest.csr` file to the CA authority of your choice (there are many vendors like GeoTrust, RapidSSL, Verisign, etc.).

**STEP 4:** After you receive the certificate, copy it on the server (in this example, the certificate will be temporarily stored in `/root/newcert.pem`).

**STEP 5:** Open the `/usr/local/dnsmanager/admin/conf/httpd.pem` file with your favorite text editor (e.g. NotePad++, jEdit) and remove the lines starting with:

```
-----BEGIN CERTIFICATE-----
```

and ending with:

```
-----END CERTIFICATE-----
```

**STEP 6:** Copy the new certificate by executing the command:

```
cat /root/newcert.pem >> /usr/local/dnsmanager/admin/conf/httpd.pem
```

**STEP 7:** Restart 4PSA DNS Manager HTTP server using:

```
/etc/init.d/dnsmanager restart
```

## Related articles

- [How to install a LetsEncrypt SSL certificate in VoipNow](#)
- [How to avoid the SSL Poodle attack](#)
- [How to change the SSL certificate in VoipNow](#)
- [Where can I find the VoipNow certificates](#)
- [How to change my 4PSA DNS Manager HTTP server SSL certificate](#)