

How to use a different partition for voicemail and call recordings storage

Applies to VoipNow 3 and higher!

This article describes how to use a different partition from the one where VoipNow is installed to store your voicemails and call recordings.

How to partition a new hard disk

After adding a new hard disk to the server, you will have to partition it accordingly. In order to do so, you need to run:

```
cat /proc/partitions
```

This command should list all existing hard disks and partitions. If you already have a `/dev/sda` (common for SATA devices), then whenever you add another device, it should be displayed as `/dev/sdb`.

STEP 1: If the device is present, you need to partition it using:

```
fdisk /dev/sdb
```

For example:

```
Command (m for help): n
Command action
e extended
p primary partition (1-4)
e

Partition number (1-4): 1
First cylinder (1-2654, default 1):
Using default value 1

Last cylinder or +size or +sizeM or +sizeK (1-2654, default 2654):
Using default value 2654

Command (m for help): w (Write and save partition table)

The partition table has been altered!

Calling ioctl() to re-read partition table. Syncing disks.
```

STEP 2: Then you need to format the partition as **ext4** using the following command:

```
mkfs -t ext4 /dev/sdb1
```

STEP 3: Create a directory for the new partition and mount it:

```
mkdir /newdrive
mount /dev/sdb1 /newdrive
```

Check the [How to Copy the Old Files to the New Location](#) section in case you want to copy old recordings/voicemails to the new hard disk.

STEP 4: Bind the **Recordings** directories to a new directory by using the following command lines:

```
service asterisk stop
mkdir -p /newdrive/monitor && mount --bind /newdrive/monitor /var/spool/asterisk/monitor
mkdir -p /newdrive/voicemail && mount --bind /newdrive/voicemail /var/spool/asterisk/voicemail
service asterisk start
```

Now, all new voicemails and recordings will be written into the new directory called `/newdrive`.

To verify if the bind was done correctly, run `mount` and check if `/var/spool/asterisk/monitor` and `/var/spool/asterisk/voicemail` are present.

To unmount the directories, run:

```
umount /var/spool/asterisk/monitor
umount /var/spool/asterisk/voicemail
```

STEP 5: Make sure the new directories will be owned by Asterisk and their permissions are set to 750. For example:

```
chown asterisk.asterisk /newdrive/monitor
chown asterisk.asterisk /newdrive/voicemail
chmod 750 /newdrive/voicemail
chmod 750 /newdrive/monitor
```

How to make changes persistent after reboot

Add the following lines into `/etc/fstab`:

```
/dev/sdb1 /newdrive ext4 defaults 1 2
/newdrive/monitor /var/spool/asterisk//monitor bind defaults,bind 0 0
/newdrive/voicemail /var/spool/asterisk/voicemail bind defaults,bind 0 0
```

How to copy the old files to the new location

To copy old files to the new location, run:

This must be done before mounting the folders from newdrive to `/var/spool/asterisk`

```
cp -Rpf /var/spool/asterisk/monitor /newdrive/monitor
cp -Rpf /var/spool/asterisk/voicemail /newdrive/voicemail
```

Related articles

- [How to set up Ring All and Transfer to voicemail](#) (4PSA Knowledge Base)
 - [ring](#)
 - [voicemail](#)
 - [transfer](#)
 - [incoming](#)
 - [call](#)
 - [rules](#)
 - [extension](#)
 - [kb-how-to-article](#)
- [How to configure sharing policies for a user account](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [voipnow](#)
 - [sharing](#)
 - [policies](#)
 - [user](#)
 - [account](#)
 - [resource](#)
 - [voicemail](#)
 - [fax](#)
 - [call](#)
 - [recordings](#)
 - [history](#)
- [What does maximum storage mean](#) (4PSA Knowledge Base)
 - [voipnow5](#)
 - [kb-how-to-article](#)
 - [storage](#)
- [How to find files stored on the local disk](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [disk](#)
 - [storage](#)
 - [files](#)
 - [local](#)

- [How to switch from local storage to Amazon S3](#) (4PSA Knowledge Base)
 - [amazon](#)
 - [s3](#)
 - [voipnow](#)
 - [storage](#)
 - [local](#)
 - [bucket](#)
 - [kb-how-to-article](#)
- [Troubleshooting voicemail not answering calls from ICRs](#) (4PSA Knowledge Base)
 - [voicemail](#)
 - [icr](#)
 - [kb-troubleshooting-article](#)
- [How to set NFS with VoipNow](#) (4PSA Knowledge Base)
 - [distributed](#)
 - [architecture](#)
 - [nfs](#)
 - [infrastructure](#)
 - [controller](#)
 - [ic](#)
 - [nodes](#)
 - [storage](#)
 - [disk](#)
 - [kb-how-to-article](#)
- [How to check voicemail messages using a Voicemail Center extension](#) (4PSA Knowledge Base)
 - [voicemail](#)
 - [messages](#)
 - [kb-how-to-article](#)
 - [center](#)
 - [mailbox](#)
- [How to force MWI notifications for phones that do not subscribe to the service](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [mwi](#)
 - [notifications](#)
 - [voicemail](#)
 - [phone](#)
 - [devices](#)
- [How to set up the Voicemail](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [voicemail](#)
 - [phone](#)
 - [terminal](#)
 - [enable](#)
 - [extension](#)
- [Troubleshooting the MWI LED remaining on even if there are no voicemail messages](#) (4PSA Knowledge Base)
 - [mwi](#)
 - [led](#)
 - [kb-troubleshooting-article](#)
 - [message](#)
 - [waiting](#)
 - [voicemail](#)
- [Troubleshooting not receiving voicemail notifications](#) (4PSA Knowledge Base)
 - [kb-troubleshooting-article](#)
 - [voicemail](#)
 - [notifications](#)
 - [messages](#)
 - [email](#)
 - [templates](#)
- [How to transfer incoming calls to another extension voicemail](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [voipnow5](#)
 - [incoming](#)
 - [calls](#)
 - [transfer](#)
 - [voicemail](#)
 - [extension](#)
- [How does call limitation work](#) (4PSA Knowledge Base)
 - [kb-how-to-article](#)
 - [voipnow](#)
 - [call](#)
 - [limitation](#)
- [Understanding the Call Reports in VoipNow](#) (4PSA Knowledge Base)
 - [call](#)
 - [reports](#)
 - [voipnow5](#)
 - [kb-how-to-article](#)