

# How to change the From header for messages sent by Postfix

Applies to VoipNow 3.X.X!

If for any reason, you need to replace the email sender with another name/email address, you must follow the recommendations below.

## Step-by-step guide

1. Add the following line in `/etc/postfix/main.cf`. All outgoing emails will have this address in the FROM field, but the name of the sender will not be modified. Replace `<FQDN>` with your fully qualified domain name.

```
sender_canonical_maps = static:no-reply@<FQDN>
```

2. To modify the name as well, you need to create a file in `/etc/postfix/header_checks` which contains this line:

```
/^From:[[:space:]]+(.*)/ REPLACE From: "Your Name" <email@company.com>
```

3. Then run the following commands:

```
cd /etc/postfix
postmap header_checks
postconf -e 'smtp_header_checks = regexp:/etc/postfix/header_checks'
service postfix reload
```

## Related articles

- [Troubleshooting not receiving email notifications from the VoipNow server](#)
- [How to change the From header for messages sent by Postfix](#)
- [Location and configuration files for VoipNow logs](#)