

# How to set up a SIP channel to interconnect with a SpeakUp account

Applies to VoipNow 3 and higher!

This article describes the steps required for setting up a SIP channel that you can use to interconnect with your SpeakUp account.

## Step-by-step guide

This is what you need to do if you want to configure a SIP channel that can connect with your SpeakUp account:

**STEP 1:** Log in the VoipNow interface and click on **Channels** in the side menu. The **Channel Management** page will open.

**STEP 2:** Click the **Add new SIP channel** icon and set it up as described here:

- **Clone settings from channel:** --
- **Name:** Fill in the desired channel name, for example *SpeakUp Channel*.
- **I want to configure the channel:** Select manually from the drop-down list.
- **Send calls to:** sip.speakup.nl
- **Accept calls from IPs/network:** 193.169.139.0/255.255.255.0
- **Username:** your\_sip\_username
- **Password:** your\_sip\_password
- **Confirm password:** your\_sip\_password
- **Do not register:** unselected
- **Concurrent calls (outgoing+incoming):** Fill in the number of channels you purchased, both for incoming and outgoing calls (e.g.: 10).
- **Charging plan:** Choose either *Free* or *Paid*, depending on your requirements. If you select *Paid*, then do not forget to add costs to the channel!
- **Channel capabilities:** Both
- **DTMF mode:** RFC2833
- **Behind NAT:** Select this checkbox if the channel is located behind a NAT (Network Address Translation) router.
- **CallerID for outgoing calls:** It should not be needed, so leave this text box empty.
- **From domain:** speakup.nl
- **Qualify value:** 300ms
- **Trusted channel:** selected
- **Trust Remote-Party-ID SIP header:** selected
- **Send Remote-Party-ID SIP header:** selected
- **Channel codecs:** Select the corresponding checkboxes for the *ulaw*, *alaw*, *g729* codes.
- **Use MD5:** unselected

You can leave the fields not mentioned in this example as they are or you can customize them according to your requirements.

**STEP 3:** Select the **Set up the public phone numbers assigned to the channel** checkbox in order to add the number(s) you have purchased.

**STEP 4:** Click **OK**.

**STEP 5:** Use the **Add Public Phone Numbers to Channel {channel\_name}** to define the numbers. Make sure you add them correctly!

The SpeakUp number format is:

318877xxxxx

## Related articles

- [Understanding and blocking ghost calls](#)
- [How to monitor VoipNow with Homer](#)
- [How to use Homer capture agents with VoipNow](#)
- [How to change music on hold for an extension](#)
- [How SIP forking works in VoipNow](#)