

How to set up a master-slave replication in 12 easy steps

Applies to VoipNow 3.X and higher!

Every time an API request is sent or a call report is generated, the SQL server receives a query. As a result, the load on the server is affected by the number of requests and the volume of data that should be returned by the SQL server.

By default, VoipNow is able to send all the read requests to a slave node and all the inserts to the master node. Basically, every time a user wants to generate a call report for an entire month, his request will be directed to the slave server. This pattern could cause problems if the replication of the data does not happen in real time and the slave remains behind the master. The MWI and presence notifications in particular are most affected.

To avoid this kind of issues, the latency between those two nodes must be as small as possible. This article will help you set up a replication between two SQL servers.

Step-by-step guide

Before taking each step, make sure that you have both SQL nodes installed as recommended in [our documentation for distributed environments](#). Another mandatory condition is that both nodes are Online. Your interface settings should look as shown in the image below.

The screenshot shows the 'Cloud Management' interface. Under 'Infrastructure Operations', there are three buttons: 'Add Node', 'Infrastructure Properties', and 'Storage Configuration'. Below this is the 'Node Listing' table:

Status	Node	Role(s)	Shard/Group	IP Addresses
Online	c4ef5d9841	SQL	main	10.150.12.18
Online	d50l9fxdpp	SQL	main	10.150.12.32
Online	4af4d4875e	Distributed DB Elasticsearch Web Management Interface Infrastructure Controller Jabber Mail PBX Queue SIP Worker	N/A	10.150.12.35

1. Edit MySQL config file on the master server: `/etc/my.cnf`. At the end of the file, add the following lines. Then save changes and restart MySQL.

```
SQL Master - /etc/my.cnf  
  
#replication  
expire_logs_days=30  
server-id = 1  
log-bin=/var/lib/mysql/mysql-bin.log  
log_bin_trust_function_creators=1  
binlog_format=MIXED
```

2. Add the MySQL user destined for replication with the appropriate rights. Log in on MySQL CLI and run the following command:

```
SQL Master - SQL console  
  
GRANT SELECT, PROCESS, FILE, SUPER, REPLICATION CLIENT, REPLICATION SLAVE, RELOAD ON *.* TO replica%'  
identified by 'password'; FLUSH PRIVILEGES;
```

Password change



Replace the `password` string with a custom, complex password. You can generate one using <http://passwordsgenerator.net/> or a similar site.

3. Stop the MySQL service on the slave server:

SQL Slave - command line

```
service mysql stop
```

- Go back to the master node and run the following command. In order to synchronize the folders, you will have to provide the root password for connecting via SSH on the slave server.

SQL Master - command line

```
rsync -varPe ssh /var/lib/mysql root@<slave_ip>:/var/lib/
```

IP replacement



Change the <slave_ip> with your SQL slave IP address.

- Lock the database to prevent any new changes.

SQL Master - SQL console

```
FLUSH TABLES WITH READ LOCK;
```

- Check status on master server:

SQL Master - SQL console

```
mysql> show master status;
```

```
+-----+-----+-----+-----+
| File                | Position | Binlog_Do_DB | Binlog_Ignore_DB |
+-----+-----+-----+-----+
| centos-6-b64-test-bin.000001 | 43311833 |              |                   |
+-----+-----+-----+-----+
```

- Again, synchronize the MySQL home directory on the slave server. Run the *rsync* command on the master server one more time.

SQL Master - command line

```
rsync -varPe ssh /var/lib/mysql root@<slave_ip>:/var/lib/
```

- Unlock tables.

SQL Server - SQL console

```
UNLOCK TABLES;
QUIT;
```

- Edit MySQL config file on the slave server: */etc/my.cnf*. At the end of the file, add the following lines:

SQL Slave - /etc/my.cnf

```
expire_logs_days=30
log_bin=/var/lib/mysql/mysql-bin.log
server-id=2
max_allowed_packet=128M
binlog_format=MIXED
log_bin_trust_function_creators=1
```

10. Start MySQL service on the slave server, connect to MySQL CLI and run the following command:

SQL Slave - SQL console


```
stop slave;
```

11. Set the master parameters on the slave server.

SQL Slave - SQL console

```
change master to master_host='<master_ip>', master_user='replica', master_password='<password>',
MASTER_LOG_FILE='<log_file>', MASTER_LOG_POS=<position>;
```

Enter correct configuration parameters

Replace  `<master_ip>` with your SQL master IP address.

Replace `<password>` with the previously generated password.

Replace `<log_file>` with the log file name displayed in step 6 (`centos-6-b64-test-bin.000001` in our example).

Replace `<position>` with the position index displayed in step 6 (`43311833` in our example).

Then disable the partition update event and start the slave node:

SQL slave - SQL console

```
alter event partition_update disable;
start slave;
```

12. Check the slave status.

SQL slave - SQL console

```
mysql> show slave status\G;
***** 1. row *****
..
Slave_IO_Running: Yes
Slave_SQL_Running: Yes
..
Exec_Master_Log_Pos: 43315418
..
```

A successful replication is indicated by `Slave_IO_Running` and `Slave_SQL_Running` being `Yes`. If the two parameters have different values, replication is not configured correctly.

Related articles

- [How to set up a master-slave replication in 12 easy steps](#)

- [How to use SIP trunking to connect a PBX to an extension](#)
- [How to repair crashed tables](#)
- [How to allow remote MySQL connections to the VoipNow server](#)
- [How to monitor your web server performance](#)